



TestShell Studio Training

Student Handouts

Author name : Shay Cesary





Table of Contents

PREFACE	3
QUICK START	4
WHAT IS TESTING?	5
AUTHORING TESTS	7
THE WORK ENVIRONMENT	12
GLOSSARY	13
MODULES	16
RUNNING TESTS AND REGRESSIONS	21

Table of Figures

Figure 1 - The Studio Login.....	4
Figure 2 - The studio canvas with a new test	4
Figure 4 - Editing the instruction	8
Figure 3 - adding an Instruction step.....	7
Figure 5 - setting the criteria	8
Figure 6 - placing a case.....	9
Figure 7 - Adding another path to a case	9
Figure 8 - Set the "Too Hot" condition.....	10
Figure 9 - adding a message to the "TOO HOT" flow	10
Figure 10 - The finished test	11
Figure 11 - Edit a message	11
Figure 12 - The Runner Login	21
Figure 13 - Execution details.....	21

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

Preface


This document is a supplement of the TS-S TestShell Studio Basic Training. The handouts are not replacing the training presentations, but to supplement and assist users.

The basic assumption is that, the user has Studio client or standalone versions already installed on the user's PC or Laptop. This document will not be relevant if a working, TestShell Studio™ is not available.

The user is referred to as "He" for convenience only. This document aims for men and women alike.

Quick Start

To start the system, please follow the steps below:

1. Click on the Studio Icon 
(Alternative: Start Programs->QualiSystems TestShell->TestShell Studio)
2. After the splash screen finish the load up, type your credentials
(by default - User: admin Password: admin)





Figure 1 - The Studio Login

3. The Start page appears; select the option  [New Test](#) from the “Actions” section
(The middle of the document). Alternatives: Select “New Test” from the top ribbon; Create a new test on the “Tests” pane, double click to open it




Figure 2 - The studio canvas with a new test

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

What is testing?

The standard concept of testing is structured from these basic steps:

1. **Setup:** Creating the initial conditions for testing: Connections, inputs, environment, control signals, etc. This stage may include instructing users
2. **Measurement:** Reading from a device the results of the tested action. In some cases, there is a need for a device to transform physical attribute (voltage, temperature, packet rate, loss) to digital information.
3. **Analysis:** In most cases, the needed data is not readily available from the measured data. This stage can take many different forms:

- a. **Text parsing:** the information is part of a larger text, and the information needs to be extracted according to markers in the text


Ping statistics for 192.168.42.1:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 0ms, Maximum = 0ms, Average = 12ms

- b. **Graph Analysis:** the information is analyzed mathematically from the output graph (Rise time, fall time, IP3, spike, spurious, etc.)



- c. Conversions (Hex to Decimal, String to array, H/Vlookup, etc.)
4. **Decision:** Once the needed data is processed, the test can reach a decision about the results: Comparing to a 'golden' result, compare to a specification document, white/black lists, search for a specific string, upper/lower limits
 5. **Reporting:**

Display on the report, add text/image/link, add metadata tags for future BI queries

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

Step	Basic Electronics	RF	Telecom	Medical
SETUP	Set a power supply output voltage to 7.5 Voltage. Set environment chamber to 75°C	Set the input voltage, a network analyzer input and the power meter range	Set a traffic generator with TCL script. Program a router through serial port	Set a black body radiator, program a pulse and breathing simulator with VB script
MEASUREMENT	Measuring the device output voltage from an oscilloscope	Capturing the network analyzer and spectrum analyzer graphs	Read the output log. Parse the relevant information	Reading thermometer, Pulse reader and Oxygen absorption levels
ANALYSIS	Calculating Rise Time, Ripple and Output Voltage.	Calculate: Amplification, BW, IP3 and SNR. Detect spurious	Parse from the result report the loss rate, error rate. Detect DoS and load balancing problems	Compare output graphs to golden graphs – calculate correlation
DECISION	Rise time<5msec, Ripple<5%, 4.8V<Output voltage<5.2V	10dB<A<11dB .74Khz<BW<.76Khz IP3>50. Spurious less than 2dBm	No decision – test is continues	If any of signals is missing – Fail If correlation between golden and actual graphs less than 97% - fail
REPORTING	Display the scope graph and numeric results. Add the environment conditions	Display Graphs; attach system spec document and numeric results. Add user digital signature	If loss rate is less than requires – send mail to the field office hotline	Display graphs; attach numeric reads of all sensors. Attach the FDA approval note to each report

Authoring Tests

TestShell Studio test authoring is simple: Drag, drop and configure.

1.1 Scenario

Let us create a simple test – we will check if the room temperature is between 20°C to 25°C. We will ask the user to inspect a thermometer to get the temperature, we will check if the recorded temperature is within the range (20 to 25) – if it is above the limit – instruct the user to activate cooler; if it is below – instruct the user to activate heater.

1.2 Step-by-step

- a) Create a new test (see Quick Start above)
- b) From the Tools pane (right hand), select the utilities stencil, and drag the INSTRUCTION module just below the start step (see Figure 3)
Double click the instruction step to edit
- c) In the main field, type “Please type the temperature in the room (In centigrade)”
- d) Change the user output label to “Temp”
- e) Change the output type to Numeric
- f) Now, to set the limits, click on the “Set Criteria” button




Figure 3 - adding an Instruction step




Figure 4 - Editing the instruction

- g) Set the limits for the temperature (upper=Spec 1, lower=Spec 2)




Figure 5 - setting the criteria

- h) Click ok to close the module
- i) Now we need to determine if it was too hot, too cold or just right. Drag a CASE module from the Flow stencil, right after the previous module

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.




Figure 6 - placing a case

- j) By default, a case has two options. We need three (Hot, Cold and OK). Click on the right edge of the case module, and drag it to add another option
- k) Double click the case module, there are three tabs 1, 2 and default. We need to set the conditions for 1 (too hot) and 2 (too cold)




Figure 7 - Adding another path to a case

- l) Select the first condition (tab 1). In the left field, right click and select “insert variable”. Insert the output of the Instruction module *INSTRUCTION1* which we labeled *Temp*. All expressions, variables and functions are enclosed in curly brackets. So once selected – the left field will be {Instruction1.Temp}. Mark the color of the test – indicating a valid variable

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.




Figure 8 - Set the "Too Hot" condition

- m) Select the second conditions (tab 2). Use the same variable (either type or insert), change the condition sign to smaller and the value to 20
- n) From the utilities stencil, add a *MESSAGE* box to each condition flow (see Figure 9 - adding a message to the "TOO HOT" flow)
- o) Edit each message with the relevant text – for the too hot condition, add the text “PLEASE ACTIVATE COOLER”, the too cold “PLEASE ACTIVATE HEATER” and “TEMPERATURE OK” for the default case.




Figure 9 - adding a message to the "TOO HOT" flow

- p) The final test would look like Figure 10 - The finished test

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.





Figure 10 - The finished test



Figure 11 - Edit a message

- q) Run the test by clicking on  **Run**, on the ribbon

The Work Environment



1.1 Ribbon

General actions in documents: Opening, saving, clearing and window options

1.2 Control Bar

Used to 'Dry Run' a test in Studio, before launching on a runner.

1.3 Tools Stencils

The repository of modules. From here, one drag a step onto the canvas

1.4 Panes

The different explorers (Tests, UUT, Regression, watchers, etc.)

1.5 Canavs

The document authoring area, place steps and constructs to create flows.

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

Glossary

1.1 Assets

A way to handle testing resources like scripts, DLL's executables and web services. Shared assets are saved on the Database and are deployed on each runner temporarily.

1.2 Attributes

Any measurement, and many modules, can be tagged with attributes. Attributes are tags of metadata that will allow the aggregation, filtering and grouping of data in the database. Examples of attributes could be: Versions (HW/SW/FW), Test conditions, Environmental data, report sections indication, etc.

1.3 Canvas

The work area of a document. Canvases are made from blocks and separators. Place steps and constructs on a canvas to create a flow.

1.4 Construct

Some elements (Loops, Cases, parallel, lock) made from two steps – a beginning and a rendezvous step. One needs to place other steps inside the construct, as needed.

1.5 Criteria

A decision step. Criteria steps decide if the result passes or fails according to a set of conditions. It takes just one failed criteria (or a *FAIL* step) to change a report status to *FAIL*. Criteria can be added to any measurement module, or to be placed autonomously on the canvas, as a step.

1.6 Document

A collective name to everything that has a canvas (Test, Regression, Group, mini-canvass, function, etc.)

1.7 Event

A special kind of variable, allows one flow to time the activation of a parallel flow.

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

1.8 Flow

All actions in a document, start with a *START* step and flow down (and right, if needed) until no more steps are available, or reaching an *END / TERMINATE* steps. The single cascade of steps is called a flow. A document can have several flows 9either have multiple *START* steps, or branch with *PARALLEL*)

1.9 InSight®

The Business Intelligence tool of the TestShell suite. Used to query on results from Studio® Runners to create reports and web dashboards. Attributes can be used by InSight to aggregate, filter and group results in graphs, charts, OLAP cubes and web parts.

1.10 Mini-Canvas

Some modules (e.g. communications) are opened on a separate document, to create a session. This is needed as these session include multiple steps (Setting user name and passwords, selecting a long list of options, etc)

1.11 Module

Any element that can be placed on a canvas to become a step or construct. includes tools, assets, variables and tests.

1.12 Pane

A window element that appears on the screen, that can be made into a floating or docked element (Watcher, Tests, Regressions, Variables, Assets, Tools, Errors, Sessions, etc.)

1.13 Publishing Variables

Variables in a document can be published as inputs and or outputs. Once published, a variable is accessible from outside a document. One can set input variables and read output variables, when a test is used by another test as a function

1.14 Regression

A document that combines several tests to fully examine a device, service or a product.

1.15 Ribbon

A set of buttons that appear on the top of the work area and are always visible

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

1.16 **Step**

Any assigned block on the canvas. Steps can be modules or part of a construct.

1.17 **Test**

A document which does a specific thing. Tests consist of at least one flow, and can publish variables as inputs and or outputs, which allow them to be functions in other documents.

1.18 **Transformation**

An analysis step. Transformation allows parsing, calculations, conversions and more. Transformation can be added to any measurement module, or to be placed autonomously on the canvas, as a step.

1.19 **UUT**

Unit Under Test (Or DUT – for Device Under Test). A grouping element to tag tests and regressions execution. Each UUT can define parameters that all documents can use as global variables.









1.20 **Variable**

Studio®'s most basic infrastructure. A variable is a cell (or a group of cells) in memory, which can store and retrieve information. Variables can be string, numeric, event, lock or session and can be scalar, vector or a matrix of values. Variable are used throughout Studio®.

1.21 **Watchers**













Watchers appear in the watcher pane, they display in real time the values of variables (or steps) beside the canvas. Used mainly for debugging or monitoring.

Modules

Icon	Description	Tool Group
 Pass	Adds a “Pass” notification to a test report.	Analysis
 Fail	Adds a “Fail” notification to a test report. Will cause test status to turn “Fail”	
 Criteria	Determines a “Pass” or “Fail” according to a set of conditions. This is a manifestation of the DECISION step in testing theory	
 Transform	Converts, parses, transforms and manipulates numeric or textual information. This is a manifestation of the ANALYSIS step in testing theory	
 Attributes	Adds metadata (or tags) to measurements or entire tests. Attributes are very useful to aggregate, group and filter data in BI applications (like QualiSystems InSight©)	
 Text To Report	Adding text, variables, expressions, files, links and images to the report	
 Start	An obligatory step in every document. Each ‘Start’ step will start an independent flow on the document (test, group or regression)	Flow
 End	Three different verities: <u>Stop branch</u> – will stop the flow, but not any parallel flow <u>Stop Test</u> – will stop all flow in current document, but not any parallel tests <u>Stop Execution</u> – will stop all running documents.	













This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

 Loop	Repeating a flow of steps for a set number of times.	Flow
 Terminate	Will stop all execution, and will change report status to “Terminated”. Use only for emergency stops (not regular test condition).	
 Parallel	Branch the flow to two (or more) parallel flows	
 ParaLoop	run a segment of the flow several instances concurrently	
 Delay	Pause a flow to a specific set of time	
 While	Similar to loop. This construct repeats a segment of a flow as long as a condition is met	
 Case	Selecting a flow according to a set of conditions.	
 NOP	No Operation	
 GUI Automator	Recording and playing windows and web interaction. Use with a Ranorex Installation (Independent License)	GUI Automation
 Real VNC	Using a Real VNC remote client/server to perform actions on the remote machine or phone. Use with a Real VNC agent (Independent License)	
 VISA	Communications with a VISA mapped device (Serial, GPIB, LXI, VXI, etc.)	Interfaces
 SNMP	Simple Network Management Protocol	








This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

 SNMP Trap	Sets, reads and closes SNMP traps (with filters)	Network protocols
 FTP	An Files Transfer Protocol client	
 Terminal	A 'mini-canvas' module for a session of Serial, Telnet or SSH communications	
 Client	A 'mini-canvas' module to set and monitor the communication on Serial, TCP and UDP protocols	
 LabVIEW VI	Integrating National-Instruments© LabView® Virtual Instruments	Software
 Win32 DLL	Integrating a win32 DLL (C or Winapi)	
 Command Shell	Using the Microsoft© PowerShell for DOS or simple scripting	
 Group	Create an empty group (a sub test) within a test	Utilities
 File Engine	File actions (creating, loading, copying, renaming, searching, etc.)	
 MatShell	A mathematical scripting tool	
 Message	A pop up message – for warning, instructing, guiding and alerting a user	
 Instruction	Getting information from a user	




This material is confidential and proprietary.





Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

 Test	using another test as a function within the current document	Utilities
 Assign Variable	Set a variable to a fixed or calculated value(s)	Variables
 Set Session	Setting a session variable to activate a session	
 End Session	Setting a session variable to stop (kill) a session	
 Lock	A mutual exclusive construct. This will make a segment of flow to be exclusive from parallel LOCK segments	
 Set Event	Setting an Event type variable to either ON (default) or OFF . This will trigger the corresponding WAIT FOR EVENT modules	
 Wait For Event	Pausing a specific flow until a SET EVENT (above) is triggered in a parallel flow	

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

Icon	Description	Tool Group
 Write	Send information using the selected protocol	Network Tools (Mini Canvas)
 Read	Collects the receive buffer of the selected protocol	
 Terminal Command	Combination of Write and Read. The module will send information and collect the response	


Icon	Description	Tool Group
 Inspect	Measuring system elements and allow Javascript execution	GUI Tools (Mini Canvas)
 Keyboard	create a key press sequence	
 Mouse	Create mouse operations on selected elements	
 Validate	Validating element property values	

This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.

Running Tests and Regressions

To run a test or regression in the RUNNER environment, please follow the following steps:

1. Click on the Runner Icon 
(Alternative: Start Programs->QualiSystems TestShell->TestShell Runner)
2. After the splash screen finish load, type your credentials
(by default - User: admin Password: admin)







Figure 12 - The Runner Login

3. Select the test (or regression) to run by clicking on the *OPEN TEST*  or *OPEN REGRESSION*  buttons on the ribbon (To switch, click in the black triangle near the button )
4. Once the document loads, fill the execution details:





Figure 13 - Execution details

To run the document, click on the RUN button in the control bar (or click F5)



This material is confidential and proprietary.

Any unauthorized reproduction, use or disclosure of this material or any part thereof, is strictly forbidden.